

**CREX Table C - Data description operators for edition 1**

REFERENCE	OPERAND	OPERATOR NAME	OPERATOR	Status
C 01	YYY	Data width replacement	YYY characters (from 000 to 999) replace specified Table B data width	Operational
C 02	YYY	Scale factor replacement	YYY (from -99 to 999) replaces the specified Table B scale factor	Operational
C 05	YYY	Character insertion	YYY characters (from 001 to 999), including spaces, are inserted as a data field	Operational
C 07	YYY	Unit replacement	Change unit to unit defined in Common Code Table C-6 by code figure equal to YYY, for example: YYY = 040 changes unit to Celsius YYY = 741 changes unit to km h <sup>-1</sup> YYY = 201 changes unit to knot YYY = 740 changes unit to km	Operational
C 60	YYY	National letters insertion (see Note)	YYY national letters including spaces are inserted as a data field.	Operational

Note: (see)

**CREX Table C - Data description operators for edition 2**

REFERENCE	OPERAND	OPERATOR NAME	OPERATOR	Status
C 01	YYY	Data width replacement	YYY characters (from 000 to 999) replace specified Table B data width	Operational
C 02	YYY	Scale factor replacement	YYY (from -99 to 999) replaces the specified Table B scale factor	Operational
C 05	YYY	Character insertion	YYY characters (from 001 to 999), including spaces, are inserted as a data field	Operational
C 07	YYY	Unit replacement	Change unit to unit defined in Common Code Table C-6 by code figure equal to YYY, for example: YYY = 040 changes unit to Celsius YYY = 741 changes unit to km h <sup>-1</sup> YYY = 201 changes unit to knot YYY = 740 changes unit to km	Operational
C 41	000	Define event	This operator denotes the beginning of the definition of an event (see Note 2).	Operational
C 41	999	Change define event	This operator denotes the conclusion of the event definition that was begun via the previous C-41-000 operator	Operational
C 42	000	Define conditioning event	This operator denotes the beginning of the definition of a conditioning event (see Note 2)	Operational
C 42	999	Cancel define conditioning event	This operator denotes the conclusion of the conditioning event definition that was begun via the previous C-42-000 operator.	Operational
C 43	000	Categorical forecast values follow	The values which follow are categorical forecast values (see Note 3)	Operational
C 43	999	Cancel categorical forecast values follow	This operator denotes the conclusion of the definition of categorical forecast values that was begun via the previous C-43-000 operator.	Operational
C 60	YYY	National letters insertion (see Note 4)	YYY national letters including spaces are inserted as a data field.	Operational

Notes: (see)